

Windows Server[®] 2008 Administrator's Companion

*Charlie Russel and
Sharon Crawford*

To learn more about this book, visit Microsoft Learning at
<http://www.microsoft.com/MSPress/books/11840.aspx>

9780735625051

Microsoft[®]
Press

© 2008 Charlie Russel and Sharon Crawford. All rights reserved.

Table of Contents

Acknowledgmentsxxxiii
Introduction xxxv

Part I

Prepare

1 Introduction to Windows Server 2008 **3**

 Worth the Wait 4

 Server Virtualization 4

 Server Core..... 4

 PowerShell 5

 Read-Only Domain Controller..... 5

 Active Directory Domain Services..... 5

 Restartable Active Directory Domain Services 6

 Fine-Grained Password Policies..... 6

 Data Mining Tool 6

 Terminal Services..... 7

 Terminal Services Gateway 7

 Terminal Services RemoteApp..... 7

 Terminal Services Web Access 7

 Terminal Services Session Broker..... 8

 Terminal Services Drain Mode..... 8

 Server Manager 8

 Windows Server Backup..... 8

 Clean Service Shutdown..... 9

 More Security Features..... 9

 Address Space Load Randomization 9

 **What do you think of this book? We want to hear from you!**

Microsoft is interested in hearing your feedback so we can continually improve our books and learning resources for you. To participate in a brief online survey, please visit:

www.microsoft.com/learning/booksurvey/

BitLocker Drive Encryption.....	9
Windows Firewall.....	10
Network Access Protection	10
Versions of Windows Server 2008	10
Summary.....	11
2 Introducing Directory Services	13
Understanding Directory Services	13
Active Directory in Microsoft Windows Server 2008	15
Terminology and Concepts in Active Directory	16
The Active Directory Architecture.....	19
The Directory System Agent	19
Naming Formats	20
The Data Model.....	20
Schema Implementation	20
The Security Model	21
Naming Contexts and Partitions.....	22
The Global Catalog	22
Summary.....	23
3 Planning Namespace and Domains.....	25
Analyzing Naming Convention Needs.....	25
Trees and Forests	26
Defining a Naming Convention	27
Determining Name Resolution	30
Planning a Domain Structure.....	32
Domains vs. Organizational Units.....	33
Designing a Domain Structure	34
Domain Security Guidelines.....	35
Creating Organizational Units.....	36
Planning Multiple Domains.....	36
Planning a Contiguous Namespace	37
Determining the Need for a Multi-Tree Forest.....	37
Creating the Forest	37
Summary.....	38

4 Planning Deployment	39
How Information Technology Functions	40
Identifying Business Needs	41
Getting Specific	41
Seeing into the Future	41
Assessing Current Systems	42
Documenting the Network	42
Making a Roadmap	45
Defining Goals	46
Assessing Risk	47
Summary	48

Part II

Install and Configure

5 Getting Started	51
Reviewing System Requirements	51
Designing a Deployment Environment	53
Choosing an Installation Method	53
Installing Windows Server 2008	53
Automating Server Deployment	61
Installing and Configuring WDS	63
Adding Additional Images	69
Troubleshooting Installations	72
Failure to Boot from a Network Distribution Point	72
Corrupt File During Installation	74
Failure to Find a Hard Disk	75
Stop Errors	76
Summary	77
6 Upgrading to Windows Server 2008	79
Upgrade Matrix	79
Common Threads to Upgrades	80
Pre-Upgrade Steps	81
Architecture	82

Active Directory	83
Hardware Support	85
Software Support	86
Preparing Domains and Computers	87
Upgrading Clients	88
Performing the Upgrade	88
Upgrading To Windows Server 2008	89
Forest and Domain Functional Levels	94
Summary	94
7 Configuring a New Installation	95
Overview of the Tasks	96
Initial Logon	97
Configure Hardware	98
Configuring Basic Computer Information	99
Setting the Time Zone	99
Configuring Networking	101
Setting the Computer Name and Domain	103
Updating and Feedback Settings	106
Enable Updates and Feedback	106
Getting Updates	112
Customizing the Server	112
Adding the Windows PowerShell Feature	113
Enable Remote Desktop	116
Configuring Windows Firewall	117
Closing the Initial Configuration Tasks Wizard	118
Summary	119
8 Installing Server Roles and Features	121
Defining Server Roles	122
Adding and Removing Roles	130
Add a Role	131
Removing a Role	135
Adding and Removing Role Services	139
Adding Role Services	139

Removing Role Services	141
Adding and Removing Features	142
Adding Features	143
Removing Features	144
Summary	145
9 Installing and Configuring Server Core	147
Benefits of a Server Core Installation	148
Security	148
Resources	149
Installing Server Core	149
Configuration	150
Initial Configuration	150
Installing Roles	157
Managing a Server Core Computer	160
Using Windows Remote Shell	162
Using Terminal Server RemoteApp	162
Summary	164
10 Managing Printers	165
Planning Printer Deployment	166
Establishing Printer Naming Conventions	166
Creating a Location-Naming Convention	167
Creating a Print Server	168
Enabling Printer Location Tracking	169
Migrating Print Servers	172
Using the Print Migration Wizard	172
Using the Command Line	174
Installing Printers	174
Deploying Printers with Group Policy	176
Adding PushPrinterConnections Using Group Policy	177
Managing Print Jobs from Windows	179
Temporarily Stopping Print Jobs	179
Canceling Print Jobs	179
Restarting a Print Job	179

Changing a Print Job Priority	180
Moving Print Jobs	180
Managing Printers from the Command Line	181
Setting Security Options.	182
Changing Printer Availability and Group Priorities	182
Specifying a Separator Page	184
Modifying Print Spooling by Printer	185
Spool Print Documents So Program Finishes Printing Faster	186
Print Directly To The Printer	186
Hold Mismatched Documents.	186
Print Spooled Documents First	186
Keep Printed Documents	186
Modifying Spooling on a Print Server	186
Optimizing Print Server Performance	187
Changing the Print Spooling Folder Location.	187
Managing Printer Drivers.	188
Creating Printer Pools.	189
Preparing for Print Server Failure	190
Troubleshooting Printers	191
Starting at the Server	191
Starting at the Client	195
Summary.	195
11 Managing Users and Groups	197
Understanding Groups	197
Assigning Group Scopes.	198
Planning Organizational Units.	200
Creating Organizational Units	201
Moving Organizational Units.	202
Deleting Organizational Units	202
Planning a Group Strategy.	202
Determining Group Names	202
Using Global and Domain Local Groups	203
Using Universal Groups.	203
Implementing the Group Strategy	204

Creating Groups.	204
Deleting Groups.	205
Adding Users to a Group	205
Managing Default Groups and User Rights.	208
Builtin Local Groups	208
Builtin Domain Local Groups	210
Builtin Global Groups	212
Defining User Rights	213
Creating User Accounts	218
Naming User Accounts	218
Account Options	218
Passwords	219
Creating a Domain User Account	220
Creating a Local User Account	221
Setting User Account Properties	222
Testing User Accounts	223
Managing User Accounts	223
Finding a User Account	224
Disabling and Enabling a User Account.	225
Deleting a User Account.	226
Moving a User Account	226
Renaming a User Account	226
Resetting a User's Password.	227
Unlocking a User Account	227
Using Home Folders	228
Creating Home Folders on a Server	228
Providing Home Folders to Users	229
Maintaining User Profiles	230
Local Profiles	232
Roaming Profiles	232
Assigning a Logon Script to a User Profile	236
Summary.	237

12 Managing File Resources 239

Share Permissions vs. File Permissions	240
--	-----

Share Permissions	240
File Permissions	241
NTFS Permissions.....	242
How Permissions Work.....	244
Considering Inheritance	245
Configuring Folder Permissions	246
Assigning Permissions to Files.....	247
Configuring Special Permissions.....	248
Ownership and How It Works	250
Shared Folders.....	252
Using Share And Storage Management.....	252
Using the Command Line: Net Share.....	256
Publishing Shares in Active Directory.....	256
Distributed File System (DFS)	257
DFS Terminology	258
Namespace Server Requirements.....	260
Namespace Client Requirements	261
DFS Replication	262
Installing DFS Management.....	263
Creating or Opening a Namespace Root.....	265
Adding Namespace Servers.....	266
Adding DFS Folders.....	267
Changing Advanced Settings	268
Backing Up and Restoring the DFS Folder Targets.....	271
Using DFS Replication.....	271
Summary.....	280
13 Group Policy	281
What's New in Server 2008	282
Components of Group Policy	282
Group Policy Objects.....	282
Order of Implementation.....	283
Order of Inheritance	283
Creating a Group Policy Object.....	284
Editing a Group Policy Object	284

Deleting a Group Policy Object	285
Searching for a Group Policy Object	285
Using Starter GPOs	286
Group Policy Preferences	288
Using Group Policy Preferences for Windows	291
Configuring Common Options	305
Using Group Policy Preferences for Control Panel	306
Delegating Permissions on GPOs	335
Delegating Permission to Create	336
Delegating Permission to Link	336
Delegating Permission to Edit, Delete, or Modify Security	336
Disabling a Branch of a GPO	337
Refreshing Group Policy	337
Backing Up a Group Policy Object	338
Restoring a Group Policy Object	338
Using Group Policy for Folder Redirection	339
Redirecting to One Location	339
Redirecting by Group Membership	340
Removing Redirection	341
Using Resultant Set of Policy (RSoP)	341
Running an RSoP Query	342
A Planning RSoP	342
A Logging RSoP	343
Summary	343

Part III

Administer the Network

14 Managing Daily Operations 347

User Account Control (UAC) for Administration	347
The Admin Approval Mode (AAM)	348
UAC and Registry Virtualization	348
Disabling Aspects of User Account Control	349
Turning Off UAC	352
Using Microsoft Management Console 3.0	353

Setting MMC 3.0 Console Options	353
Creating an MMC Console with Snap-Ins	354
Using the New Taskpad View Wizard.	355
Distributing and Using Consoles.	356
Using MMC for Remote Administration	356
Setting Auditing Policy	357
Auditing Categories	358
Auditing Directory Service Events.	362
Enabling Auditing of AD DS Objects	363
Setting Global Audit Policy	366
Enabling Auditing	367
Using Event Viewer	370
Managing Event Logs	375
Using Task Scheduler.	377
Using the AT Command	378
Delegating Tasks	380
Summary.	381
15 Using Scripts for Consistent Administration	383
Introducing Windows PowerShell.	384
Understanding Windows PowerShell	385
Basics	386
PowerShell as a Shell	390
Cmdlets	393
Windows Infrastructure	398
The .NET Framework	398
Windows Management Instrumentation (WMI).	402
Windows Remote Management (WinRM).	404
Component Object Model (COM)	405
Creating Popup and Input Boxes	405
Exploring PowerShell	406
Get-Command	407
Get-Help	408
Get-Member	409
Data Display	410

Parameter Sets and Positional Parameters	412
Loading a Snap-in	414
Powershell Scripting Basics	414
Creating a .ps1 Script	415
Comments.	417
Variables	418
Scope	418
Strings	419
Here Strings	420
Wildcards and Regular Expressions	421
Arrays.	422
Hashtables.	424
Operators	424
Functions.	425
Conditional Statements.	426
Looping Statements.	429
Importing and Exporting From and To Files	430
Flow Control	431
Formatting Cmdlets.	432
Exiting from Scripts, Functions, and Loops	434
Dot-Sourcing	434
Passing Arguments	435
Param Statement	436
\$_ and \$input	438
Error Handling	439
Redirection Operators.	441
Type Accelerators.	442
Escaping Characters	442
Windows PowerShell Examples.	442
Typical File System Tasks.	442
Testing Whether a File or Directory Exists	443
Windows Server Backup Cmdlets	444
Examples of Managing Server Core	444
XML Support	445

Using the File Transfer Protocol (FTP)	445
Downloading a File Using HTTP	446
Sending E-mail via SMTP	446
Compressing Files	447
Dealing with Dates	447
Timer/Countdown	449
Taking Input from the Console	450
Storing Secure Information	451
Checking Services and Processes	451
Checking the Windows Event Log	453
Getting Memory and CPU Information	455
Accessing Performance Counters	456
Checking Disk Space Usage	458
Working with the Registry	459
Copying Files to Another Directory Recursively	459
Rotating Logs	460
Renaming Files	460
Scheduling Tasks	461
Running Against Multiple Targets	462
Creating XML-Formatted Data	463
Checking Open Ports	464
Head, Tail, Touch, and Tee	464
Summary	466
16 Installing and Configuring Directory Services	467
Active Directory in Windows Server 2008	467
Active Directory Domain Services	468
Active Directory Lightweight Directory Services	468
Active Directory Rights Management Services	470
Active Directory Federation Services	472
Active Directory Certificate Services	473
Installing Active Directory Domain Services	473
Prerequisites for Installing AD DS	474
Installing AD DS Using the Active Directory Domain Services Installation Wizard	476

Operating System Compatibility	477
Deployment Configuration	478
Naming the Domain	479
Setting the Windows Server 2008 Functional Levels	480
File Locations	482
Completing the Installation	483
Adding a Domain Controller to an Existing Domain	484
Verifying the Installation of AD DS	484
Advanced Options	485
Install from Media	486
Unattended Installation	487
Uninstalling AD DS	489
Installing and Configuring Read-Only Domain Controllers	492
What Are Read-Only Domain Controllers?	492
Why Use RODCs?	493
Delegating RODC Installations and Administration	493
Configuring Password Replication Policies	496
Managing AD DS with Active Directory Users and Computers	498
Viewing AD DS Objects	499
Creating a Computer Object	503
Configuring Computer Objects	503
Using Remote Computer Management	504
Publishing a Shared Folder	504
Publishing a Printer	504
Moving, Renaming, and Deleting Objects	505
Managing AD DS with Active Directory Domains and Trusts	506
Launching Active Directory Domains And Trusts	506
Managing Domain Trust Relationships	507
Specifying the Domain Manager	509
Configuring User Principal Name Suffixes for a Forest	509
Using Active Directory Sites And Services	510
AD DS Sites Overview	512
Understanding AD DS Replication	513
Launching Active Directory Sites And Services	515

Installing and Configuring Active Directory Lightweight Directory Service	521
AD LDS Overview.....	522
AD LDS Features	522
Configuring Instances and Application Partitions	523
Managing AD LDS.....	526
Configuring Replication	530
Configuring AD DS and AD LDS Synchronization	531
Summary.....	533
17 Managing Active Directory	535
Maintaining the AD DS Database	535
AD DS Data Storage	535
Garbage Collection	537
Online Defragmentation.....	537
Restartable Active Directory Domain Services	538
Offline Defragmentation of the AD DS Database.....	540
Moving Database and Transaction Log Locations	541
Backing Up AD DS.....	541
The Need for Backups.....	543
Backup Frequency	544
Performing an AD DS Backup with Windows Server Backup.....	545
Restoring AD DS	546
Removing Domain Controllers from AD DS with Ntdsutil	546
Performing a Nonauthoritative Restore of AD DS	548
Performing an Authoritative Restore of AD DS	550
Managing the AD DS Schema.....	552
Requirements for Modifying the AD DS Schema	553
Launching Active Directory Schema.....	554
Modifying the Schema	555
Managing Operations Master Roles	561
Transferring Operations Master Roles	564
Seizing Operations Master Roles.....	566
Auditing AD DS	567
Configuring the Audit Policy.....	567

Enabling Auditing of AD DS Changes	570
Summary.....	572
18 Administering TCP/IP	573
Using DHCP	574
Designing DHCP Networks	574
Adding the DHCP Server Role.....	576
Creating a New Scope.....	582
Authorizing the DHCP Server and Activating Scopes	589
Adding Address Reservations	590
Using Multiple DHCP Servers for Redundancy.....	592
Setting Up a DHCP Relay Agent.....	593
DHCP Command-Line Administration.....	595
Using DNS Server	595
Setting Up a DNS Server	596
Creating Subdomains and Delegating Authority	603
Adding Resource Records.....	605
Configuring Zone Transfers	608
Interoperating with Other DNS Servers.....	609
Setting Up a Forwarder	610
Setting Up a WINS Server	613
Summary.....	614
19 Implementing Disk Management	615
Understanding Disk Terminology	616
Overview of Disk Management.....	619
Remote Management.....	622
Dynamic Disks	622
Command Line.....	623
Adding a New Disk	623
Partitions and Volumes.....	625
Creating a Volume or Partition	626
Creating Extended Partitions and Logical Drives	631
Converting a Disk to a Dynamic Disk.....	631
Converting a Disk to a GPT Disk.....	632

Changing the Size of a Volume	633
Adding a Mirror to a Volume	637
Setting Disk Quotas	641
Enabling Quotas on a Disk	642
Setting Per-User Quotas	643
Importing and Exporting Quotas	645
Enabling File Encryption	647
Summary	649
20 Managing Storage	651
Using File Server Resource Manager	651
Installation and Initial Configuration of FSRM	652
Scheduling Storage Reports	654
Using Directory Quotas	657
Screening Files	663
Overview of SAN Manager	670
Concepts and Terminology	672
Installing Storage Manager For SANs	674
Using the Storage Manager For SANs Console	675
Managing Server Connections	676
Managing iSCSI Targets	678
Managing iSCSI Security	679
Logging In to iSCSI Targets	680
Creating and Deploying Logical Units (LUNs)	681
Extending a LUN	687
Removable Storage	689
Concepts and Terminology	689
Use and Management	693
Summary	697
21 Using Clusters	699
What Is a Cluster?	699
Network Load Balancing Clusters	700
Failover Clusters	700
New Failover Cluster Features	701

Windows Server 2008 Core	702
Cluster Scenarios	703
Web Server	703
Terminal Services	703
Mission-Critical Applications and Services	703
Requirements and Planning	704
Identifying and Addressing Goals	704
Identifying a Solution	705
Identifying and Addressing Risks	705
Making Checklists	706
Network Load Balancing Clusters	706
NLB Concepts	706
Choosing an NLB Cluster Model	707
Creating an NLB Cluster	709
Planning the Capacity of an NLB Cluster	716
Providing Fault Tolerance	717
Optimizing an NLB Cluster	717
Failover Clusters	718
Failover Cluster Concepts	718
Types of Resources	720
Defining Failover and Failback	723
Configuring a Failover Cluster	724
Planning the Capacity of a Failover Cluster	726
Creating a Failover Cluster	727
HPC Clusters	740
Summary	742

Part IV

Secure the Network

22 Planning Security	745
The Fundamental Principles of Security	745
Confidentiality	746
Integrity	747
Availability	748

The Eight Rules of Security	748
Rule of Least Privilege	749
Rule of Change Management	749
Rule of Trust	749
Rule of the Weakest Link	750
Rule of Separation	750
Rule of the Three-Fold Process	750
Rule of Preventative Action	750
Rule of Immediate and Proper Response	751
The Higher Security Mindset	751
Think in Terms of Zones	753
Create Chokepoints	754
Layer Your Security	755
Understand Relational Security	756
Divide Responsibility	759
Summary	761
23 Implementing Security	763
Introduction	763
Secure at Installation	764
Server Core	767
Roles and Features Wizards	770
Securing the Startup: BitLocker	773
Setting Up BitLocker	773
Securing the Accounts	779
Disabling the Administrator Account	780
Password Policies on Standalone Servers	781
Password Policies in Domains	781
Windows Server 2008 Firewall	785
Setting Firewall Policies Using Group Policy	786
Firewall Rule Basics	788
Rule Definitions	789
Creating a Firewall Policy	791
Windows Firewall Via Command Line	793
Additional Security Changes	795

New Groups	796
Auditing	796
LanMan Hashes and Authentication Level	797
SMBv2	797
Read Only Domain Controllers	798
Summary.....	798
24 Administering Network Access Protection	799
Why the Need for NAP?.....	799
Planning the Deployment	801
NAP Shopping List.....	801
Servers Needed for NAP.....	802
Benefits of NAP	804
Determining the Health Policy	804
Policies Checked	804
Enforcement Levels	806
Determining Exemptions	807
Testing IPsec NAP Enforcement	808
Setting Up a Certificate Server	809
Configuring the NAP Health Policy Server	818
Client Settings for NAP.....	819
IEEE 802.1x Enforcement in NAP	827
Configuring IEEE 802xz Enforcement.....	828
Configuring 802.1X Enforcement	828
The Politics of Deployment	830
Summary.....	832
25 Patch Management	833
Why It's Important.....	834
The Patching Cycle	835
Assess	836
Identify	836
Evaluate and Plan	838
Deploy	838
Repeat	839

Deployment Testing	839
Test Network Deployment	839
Beta User Deployment	840
Full Deployment	840
Obtaining Updates	841
Automatic Updates	841
Windows Server Update Services	841
Systems Center Configuration Manager	845
Third-Party Products	845
Summary	846

26 Implementing Remote Access Strategies: SSTP, VPN, and Wireless 847

Introduction	847
Network Policy Server	848
Planning for NPS	848
Start with the Policies	849
Define the Support	850
Secure Sockets Tunneling Protocol	850
The SSTP Process	851
Configuring SSTP	852
Installing the Server Authentication Certificate	858
Installing Routing And Remote Access	868
Configuring SSTP-based Connection Clients	877
Making the SSTP Connection	881
Troubleshooting Connections	883
Using NPS in Windows Server 2008	887
Configuring Remote Access Per User	887
Configuring Remote Access in the NPS Network Policy	887
Wireless Deployment	889
Prerequisites	890
Adding RADIUS Clients to the Network	892
Configuring the Access Points	893
Configuring Clients to Use Secure Wireless	894
Summary	899

Part V

Use Support Services and Features

27 Interoperability	903
General UNIX Interoperability	903
Permissions and Security Concepts	904
A UNIX File Listing	904
Symbolic Links	906
Privilege Levels	907
Basic Connectivity	908
File Transfer Protocol	908
Telnet	909
File Systems	910
Printing	912
Network File System	912
Legacy User Name Mapping	914
Server For NFS	916
Microsoft Identity Management for UNIX	923
Installing Microsoft Identity Management for UNIX	924
Subsystem for UNIX-based Applications	928
Macintosh Interoperability	932
Summary	932
28 Managing Software	933
Using the Group Policy Software Installation Extension	933
Finding the Right Mix of Services	935
Windows Installer Packages	936
Zap Files	936
Setting Up the Group Policy Software Installation Extension	939
Creating a Software Distribution Point	939
Creating a GPO for Application Deployment	940
Configuring the Group Policy Software Installation Extension	943
Working with Packages	947
Adding a Package to a Group Policy	947
Changing Application Properties	950

Applying Package Upgrades	952
Applying Package Modifications	953
Removing and Redeploying Packages	955
Using Software Restriction Policies	955
How Software Restriction Policies Work	956
Creating Software Restriction Policies	957
Windows Deployment Services	959
Summary	959
29 Working with Windows Virtualization	961
Hyper-V Overview	962
Scenarios	963
Requirements	964
Installation	965
Installing On Windows Server Core	965
Installing on Windows Server 2008	965
Initial Configuration	968
Configuring Networks	969
Server Settings	972
Creating A Virtual Machine	974
Creating a Basic VM	975
Machine Settings	978
Management Settings	994
Working With A Virtual Machine	998
Starting, Stopping, Saving, Snapshotting	998
Clipboard	999
Export/Import	1000
Summary	1003
30 Deploying Terminal Services	1005
Concepts	1007
Remote Access	1008
Central Management	1008
Requirements	1009
RAM	1009

CPU	1009
Network Utilization	1010
Capacity Planning	1010
Installation	1011
Improving the User Experience	1020
Enabling Remote Desktop for Administration Mode	1023
Installing Programs	1024
Administration	1027
Terminal Services Manager	1027
Terminal Services Configuration	1037
Terminal Services Licensing	1042
Installing Terminal Server Licensing	1042
RemoteApps	1044
TS RemoteApp Manager	1045
Adding RemoteApps	1050
Deploying RemoteApps	1052
TS Web Access	1056
Remote Desktop Web Connection	1057
TS Web Access RemoteApp Programs	1058
Summary	1059

31 Internet Information Services1061

Architecture	1062
Components	1062
Modules	1063
Installing IIS	1065
Installing Using the Server Roles Wizard	1065
Installing Using Windows Package Manager	1066
Administration Tools	1068
Internet Information Server (IIS) Manager	1068
AppCmd.exe	1071
Windows Management Instrumentation (WMI)	1073
Administrative Tasks	1073
Managing Servers	1073
Managing Sites	1084

Managing Web Applications	1093
Managing Virtual Directories	1094
Understanding Delegation and Permissions	1094
Delegating Site and Application Management	1095
Configuring Permissions to View and Manage Content	1097
Understanding the Configuration Store	1098
Using Shared Configuration	1099
Remote Administration	1099
Installing and Managing the FTP Publishing Service	1100
FTP Current Sessions	1102
FTP Directory Browsing	1102
FTP Firewall Support	1102
FTP Messages	1102
FTP SSL Settings	1102
FTP User Isolation	1102
Active Directory Federation Services (AD FS)	1103
Summary	1104

Part VI

Tune, Maintain, and Repair

32 Windows Reliability And Performance Monitor 1107

Using Resource View	1107
CPU Details	1109
Disk Details	1110
Network Details	1110
Memory Details	1110
Using Performance Monitor	1111
Adding Counters in Performance Monitor	1112
Changing the Performance Monitor Display	1114
Saving the Performance Monitor Display	1114
Connecting to a Remote Computer Using Performance Monitor	1115
Using Reliability Monitor	1115
Viewing Reliability Monitor on a Remote Computer	1116
Interpreting the System Stability Index	1117

Creating a Data Collector Set	1119
Building a Data Collector Set from a Template.....	1120
Creating a Data Collector Set from Performance Monitor	1123
Constructing a Data Collector Set Manually	1123
Creating a Data Collector Set to Monitor Performance Counters.....	1125
Scheduling Data Collection	1126
Managing Collected Data	1128
Working with Data Log Files	1129
Viewing Reports	1131
Summary.....	1132
33 Disaster Planning	1133
Planning for Disaster.....	1133
Identifying the Risks	1134
Identifying the Resources.....	1135
Developing the Responses.....	1136
Testing the Responses.....	1139
Iterating.....	1140
Preparing for a Disaster	1141
Setting Up a Fault-Tolerant System.....	1141
Backing Up the System.....	1142
System Repair.....	1142
Specifying Recovery Options.....	1144
Summary.....	1145
34 Using Backup	1147
Installing the Backup Service.....	1147
Scheduling a Backup.....	1149
Choosing Volumes to Back Up	1149
Designating a Storage Location	1149
Creating the Backup Schedule.....	1150
Implementing a Rotating Backup Set.....	1154
Modifying a Backup Schedule.....	1155
Stop Running Scheduled Backups.....	1156

Using the Backup Once Wizard	1157
Using the Wbadmin Command	1159
Wbadmin enable backup	1160
Wbadmin disable backup	1160
Wbadmin start backup	1160
Wbadmin stop job	1161
Wbadmin start recovery	1161
Wbadmin start systemstatebackup	1161
Wbadmin start sysstaterecovery	1161
Wbadmin start sysrecovery	1162
Windows Recovery Environment	1162
Wbadmin get versions	1162
Wbadmin get status	1163
Recovering Your Server	1165
Recovering Volumes	1166
Recovering Files and Folders from the Local Server	1167
Recovering Files and Folders from Another Server	1168
Recovering Applications and Data	1169
Recovering the Operating System	1171
Restoring a Backup Catalog	1173
Summary	1174

35 Planning Fault Tolerance and Avoidance1175

Mean Time to Failure and Mean Time to Recover	1176
Protecting the Power Supply	1177
Local Power Supply Failure	1178
Voltage Variations	1179
Short-Term Power Outages	1182
Long-Term Power Outages	1182
Disk Arrays	1183
Hardware vs. Software	1183
RAID Levels for Fault Tolerance	1183
Hot-Swap and Hot-Spare Disk Systems	1189
Distributed File System	1190
Clustering	1190

Network Load Balancing	1190
Failover Clustering	1190
Summary	1191
36 Managing the Registry	1193
Introducing the Registry	1193
The Origins of the Registry	1194
How Registry Data Is Used	1195
Functional Changes in Windows Server 2008	1196
Understanding the Registry's Structure	1198
The Root Keys	1201
Major Subkeys	1203
How Data Is Stored	1206
Creating Registry Items with the Registry Wizard	1209
Using the Registry Editors	1211
A Whirlwind Tour of the Registry Editor	1211
A Whirlwind Tour of Reg	1220
Backing Up and Restoring the Registry	1221
Choosing a Backup Method	1221
System Recovery	1222
Summary	1222
37 Troubleshooting and Recovery	1223
Determining Priorities	1223
Recovering a System	1225
Identifying Possible Causes	1225
Rolling Back a Device Driver	1226
Recovering Your Server	1227
Recovering Volumes	1227
Recovering Files and Folders from the Local Server	1229
Recovering Files and Folders from Another Server	1229
Recovering Applications and Data	1231
Recovering the Operating System	1233
Recovering the System State	1234
Using System Information	1236

Verifying the Status of Services1236

Using the System Configuration Utility1239

Using the System File Checker1240

Using the Shutdown Event Tracker.....1241

Summary.....1242

A Interface Changes from Windows Server 2003.....1243

B Optional Components.....1247

C Understanding TCP/IP v41257

About the Authors1281

Index.....1283



What do you think of this book? We want to hear from you!

Microsoft is interested in hearing your feedback so we can continually improve our books and learning resources for you. To participate in a brief online survey, please visit:

www.microsoft.com/learning/booksurvey/

Chapter 9

Installing and Configuring Server Core

Benefits of a Server Core Installation	148
Installing Server Core.....	149
Configuration	150
Initial Configuration.....	150
Managing a Server Core Computer.....	160
Summary	164

The usual progression for an operating system (or an application, for that matter) is to grow and add features, sometimes well beyond what any of us want or need. Windows Server 2008 reverses that trend with a completely new installation option—Server Core. When you install Windows Server 2008, regardless of which edition you're installing, you have the option of choosing a full installation, with everything, or just the Server Core portion.

Server Core is just the essentials, with little or no graphical interface. The logon provider has the same graphical look, but then, when you've logged in, all you see is a single command-shell window, as shown in Figure 9-1.




Figure 9-1 The Windows Server 2008 Core desktop.

Note For improved readability in screen shots used here and in the rest of the book, we've changed the default color scheme for Command Prompt windows to dark blue text on a white background.

Benefits of a Server Core Installation

All Windows Server 2008 editions support Server Core, with the exception of Compute Cluster Edition. And installing Server Core doesn't give you a break on the cost of the license—it's exactly the same license and media as the full Windows Server 2008 installation. At install time, you simply choose which edition you are installing. So, if you don't save any money, and you don't have special media, and you have reduced functionality, why in the world would you choose Server Core over the full product? It's simple, really: security and resources. Let's take a look at those two in a bit more depth before we go on to the details of how to actually install and configure Server Core.

Security

In the old days, whenever you installed Windows Server, it automatically installed just about everything that was available, and turned on all the services that you were likely to need. The goal was to make installation as simple as possible, and this seemed like a good idea at the time. Sadly, the world is not a friendly place for computers any more, and that approach is no longer safe or wise. The more services that exist, and the more services that are enabled, the more attack vectors the bad guys have to work with. To improve security, limiting the available attack surfaces is just good common sense.

In Server Core, Microsoft has completely removed all managed code, and the entire .NET Framework. This leaves a whole lot fewer places for possible attack. This does, obviously, impose some severe limits on what you can and can't do with a Server Core installation. And it also means that there isn't any PowerShell possible, which in our opinion is easily the biggest limitation of Server Core—but one that we hope will be resolved in a later version of Windows Server.

The default installation of Server Core has only less than 40 services running. A typical full Windows Server 2008 installation, with one or two roles enabled, is likely to have 60 or even 70 or more services running. Not only does the reduced number of services limit the potential attack surface that must be protected, but it also limits the number of patches that are likely to be required over the life of the server, making it easier to maintain.

Resources

The second major benefit to running Server Core is the reduced resources required for the base operating system. While the official requirements for installing Windows Server 2008 are the same for Core as for a full installation, the effective numbers are significantly less, in our experience—with the exception of the disk space required (only 2 to 3 GB of HD space for a running Core installation). Plus with the limited subset of tasks that you can perform, we think Server Core is ideal for running those infrastructure tasks that everyone runs, and that don't require much interaction over time. Tasks such as DHCP, DNS, and, increasingly, virtualization. Now if it just had PowerShell...

Installing Server Core

Installing Windows Server 2008 Server Core is ultimately the same as installing the full graphical version of Windows Server 2008. The installation engine is the same, and the only difference occurs during the install, when you have to choose which version of Windows Server 2008 to install, as shown in Figure 9-2.




Figure 9-2 During initial installation, you make an irrevocable choice between Server and Server Core.

Once installation completes, you're presented with the initial logon screen. Log on as Administrator, with no password, and you'll be immediately prompted to change the password and then logged on to the desktop, as shown earlier in Figure 9-1. All initial configuration takes place from the command line, though once you've configured the basics, you'll be able to use familiar management consoles remotely.

You can use an unattend.xml file to automate the initial install and configuration of your Server Core installation. For details on the settings and syntax of unattend.xml, see <http://go.microsoft.com/fwlink/?LinkId=81030>.

Configuration

You can do all configuration tasks for Server Core at the command line, and all the initial tasks must be done at either the command line or as part of the installation process by using an unattend.xml script. Once you're performed these initial configuration tasks, you can then use regular Windows management consoles to manage the additional settings. Unfortunately, there isn't a single command shell for the tasks, but a collection of old favorites, each with a different behavior and syntax.

Initial Configuration

The initial steps you'll need to perform on a Server Core installation will depend somewhat on your intended use of the installation, but we think that the following ones are the most obvious:

- Set a fixed IP address.
- Change the server name to match your internal standards.
- Join the server to a domain.
- Change the default resolution of the console.
- Enable remote management through Windows Firewall.
- Enable remote desktop.
- Activate the server.

We'll walk through these steps for you, and leave you with a couple of basic scripts that you can modify to automate these tasks for your environment. Table 9-1 contains the settings we'll be using during this install scenario.

Table 9-1 Settings for Initial Server Core Configuration (Example)

Setting	Value
IP Address	192.168.51.4
Gateway	192.168.51.1
DNS Server	192.168.51.2
Server Name	Hp350-core-04

Table 9-1 Settings for Initial Server Core Configuration (Example)

Setting	Value
Domain To Join	example.local
Default Desktop Resolution	1024x768
Remote Management	Enable for Domain Profile
Windows Activation	Activate

Set IP Address

To set the IP address for the server, you need to use the **netsh** command-line tool. Follow these steps to configure TCP/IP:

1. From the command window, use **netsh** to get the “name” (index number) of the network card.

```
netsh interface ipv4 show interfaces
```

2. The result will be something like the following:

```
C:\Users\administrator>netsh interface ipv4 show interfaces
```

Idx	Met	MTU	State	Name
2	10	1500	connected	Local Area Connection
1	50	4294967295	connected	Loopback Pseudo-Interface 1

The Idx value for your real network card (2, in this case) will be used as the name value in future commands for **netsh**.

3. Now, using the Idx value from step 2, run the following **netsh** command:

```
netsh interface ipv4 set address name="<Idx>" source=static
address=<IP Address> mask=<netmask>
gateway=<IP Address of default gateway>
```

Note The **netsh** lines above, and in examples below, are actually one long command line, but we had to break them (and indent subsequent lines) because of the limitations of the printed page. And it's not just **netsh** that is a problem—most of the commands you end up having to use with Server Core are long and will be artificially broken in this chapter.

4. Next, specify the DNS server for the adapter, using **netsh** again:

```
netsh interface ipv4 add dnsserver name="<Idx>"
address=<IP Address of DNS Server> index=1
```

5. For secondary DNS servers, repeat the command in step 4, increasing the index value by one each time.

Renaming the Server and Joining to a Domain

The next step in initial configuration is assigning the name of the server and joining it to a domain. During initial installation of Windows Server 2008, an automatically generated name is assigned to the server and the server is placed in the WORKGROUP workgroup. You'll want to change this to align the computer name with your corporate naming policy and join the server to the correct domain and Organizational Unit. Our naming policy here has three parts: the model of server, the functional role, and a number reflecting its IP address. Thus the Server Core computer we're building in this chapter is named hp350-core-04: it's a Hewlett Packard ML 350 G5 server, it is running Server Core, and the final octet of its IP address is four. Your server naming convention will undoubtedly be different, but the important thing is to be consistent. Our domain for this book is example.local.

To change the name of the server and join it to the example.local domain, follow these steps:

1. From the command prompt, use the **netdom** command to change the name of the server:

```
netdom renamecomputer %COMPUTERNAME% /newname:<newname>
```

2. After you change the name, you must reboot the server.

```
shutdown /t 0 /r
```

3. After the server restarts, log on to the Administrator account.
4. Use the **netdom** command again to join the domain.

```
netdom join %COMPUTERNAME% /DOMAIN:<domainname>
/userd:<domain admin account> /password:*
```

5. You'll be prompted for the password for the domain administrative account you used. Enter the password. When the domain join has succeeded, you'll again need to reboot the server.

```
shutdown /t 0 /r
```

6. After the server restarts, log back on to a domain administrator's account. (You'll need to click Change User because the server will default to the local administrator account.)

Under the Hood Scripting Initial Configuration

If you set up more than one or two Server Core computers, you'll quickly get tired of doing all this interactively from the command prompt. We know we did. You have the choice of either using an unattend.xml file to set options during the install or using simple scripts to automate the process. Both work, and both have their adherents, but we tend to use scripts after the fact. You can modify the following three scripts (which you'll also find on the companion CD) for your environment to automate the initial TCP/IP, server name, and domain join steps.

The first script sets the IP address, sets the DNS server, and changes the server name.

```
echo off
REM filename: initsetup1.cmd
REM
REM initial setup for a Server 2008 Server Core installation.
REM command file 1 of 3
REM
REM Created: 4 September, 2007
REM ModHist: 5/9/07 - switched to variables (cpr)
REM
REM Copyright 2007 Charlie Russel and Sharon Crawford. All rights reserved.
REM You may freely use this script in your own environment, modifying it
REM to meet your needs. But you may not re-publish it without permission.

REM first, set a fixed IP address. You'll need to know the index number
REM of the interface you're setting, but in a default Server Core install,
REM with only a single NIC, the index should be 2. To find the index,
REM you can run:
REM     netsh interface ipv4 show interfaces
REM

SETLOCAL
REM Change the values below to match your needs
SET IPADD=192.168.51.4
SET IPMASK=255.255.255.0
SET IPGW=192.168.51.1
SET DNS1=192.168.51.2
SET NEWNAME=hp350-core-04

netsh interface ipv4 set address name="2" source=static
address=%IPADD% mask=%IPMASK% gateway=%IPGW%

REM Next, set DNS to point to DNS server for example.local.
REM 192.168.51.2 in this case
netsh interface ipv4 add dnsserver name="2" address=%DNS1% index=1
```

```
REM Now, we need to change the computer name. After we're done, the server
REM must be restarted, and we can continue with the next batch of commands.
REM we use the /force command here to avoid prompts
netdom renamecomputer %COMPUTERNAME% /newname:%NEWNAME% /force
```

```
@echo If everything looks OK, the it's time to reboot
pause
REM now, shutdown and reboot. No need to wait.
shutdown /t 0 /r
```

The second script we use is to actually join the server to the domain.

```
@echo off
REM Filename: initsetup2.cmd
REM
REM initial setup for a Server 2008 Server Core installation.
REM command file 2 of 3
REM
REM Created: 4 September, 2007
REM ModHist:
REM
REM Copyright 2007 Charlie Russel and Sharon Crawford. All rights reserved.
REM You may freely use this script in your own environment, modifying it
REM to meet your needs. But you may not re-publish it without permission.
```

```
SETLOCAL
SET DOMAIN=example.local
SET DOMADMIN=Administrator
```

```
REM Join the domain using the netdom join command. Prompts for password
REM of domain administrator account set above
```

```
netdom join %COMPUTERNAME% /DOMAIN:%DOMAIN% /userd:%DOMADMIN% /password:*
```

```
REM now, shutdown and reboot. No need to wait, and that's all we can do
REM at this time
```

```
shutdown /t 0 /r
```

Finally, use the third script to enable remote management and activate the server.

```
echo off
REM initsetup3.cmd
REM
REM initial setup for a Server 2008 Server Core installation.
REM command file 3 of 3
REM
REM Created: 4 September, 2007
REM ModHist:
REM
```

```
REM Copyright 2007 Charlie Russel and Sharon Crawford. All rights reserved.
REM You may freely use this script in your own environment, modifying it
REM to meet your needs. But you may not re-publish it without permission.

REM Use netsh to enable remote management through the firewall for the
REM domain profile. This is the minimum to allow using remote MMCs to work
REM from other computers in the domain.

netsh advfirewall set domainprofile settings remotemanagement enable

REM allow remote administration group
netsh advfirewall firewall set rule group="Remote Administration" new
    enable=yes

REM Allow remote desktop
REM (also works with group="Remote Desktop" instead of name=)
netsh advfirewall firewall set rule name="Remote Desktop (TCP-In)" new
    enable=yes

REM Enable Remote Desktop for Administration, and allow
REM downlevel clients to connect
cscript %windir%\system32\scregedit.wsf /AR 0
cscript %windir%\system32\scregedit.wsf /CS 0

REM Now, run the activation script
REM No output means it worked
Slmgr.vbs -ato
```

Setting Desktop Display Resolution

To set the display resolution for the Server Core desktop, you need to manually edit the registry. We'd give you a script to do it, but it is dependent on correctly identifying the specific GUID for your display adapter. Not something we want to automate. So, to change the resolution on your Server Core desktop, follow these steps:

1. Open **regedit**.
2. Navigate to **HKLM\System\CurrentControlSet\Control\Video**.
3. One or more GUIDs is listed under Video. Select the one that corresponds to your video card. Hint: They each have a device description under the 0000 key that can sometimes help.
4. Under the GUID for your video card select the 0000 key, and add a **DWORD DefaultSettings.XResolution**. Edit the value to the X axis resolution you want. For a width of 1024 pixels, use 400 hexadecimal, as shown in Figure 9-3.




Figure 9-3 Editing the display resolution value for the X axis

5. Add a DWORD DefaultSettings.YResolution. For height of 768 pixels, use 300 hexadecimal.

Note In some cases, these keys will already exist. If they do, you can simply change their value as necessary.

6. Exit the registry editor and log off using the following:
`shutdown /l`
7. Once you log back on, the new display settings will take effect.

Enabling Remote Management

To allow access to the familiar graphical administration tools, you need to enable them to work through Windows Firewall. This requires another set of **netsh** commands. Use the following steps to enable remote administration and Remote Desktop:

1. From the command prompt, use the **netsh** command to enable remote management:

```
netsh advfirewall set domainprofile settings remotemanagement enable
```

2. Now, enable the Remote Administration group of firewall rules.

```
netsh advfirewall firewall set rule group="Remote Administration" new  
enable=yes
```

3. Finally, life is easier when you can connect using remote desktop, so let's enable that, too:

```
netsh advfirewall firewall set rule name="Remote Desktop (TCP-In)" new  
enable=yes
```

You should now be able to do additional management using familiar graphical tools from another server but connecting to the Server Core computer.

Activating the Server

The final step in basic configuration of the Server Core computer is to activate it. This requires using a Visual Basic script, which is provided. Use the following command:

```
Slmgr.vbs -ato
```

Note All the basic initial setup commands for Server Core are included in the three scripts described in the Under The Hood sidebar, and are also available on the CD that comes with the book.

Installing Roles

Windows Server 2008 Core doesn't support all the possible roles and features of the full graphical Windows Server, but it does support the most important infrastructure roles. We think one of the most compelling scenarios for Server Core is as a remote site server to enable basic functionality at a remote site where there isn't anyone on site to administer it. By combining the DHCP Server, DNS Server, File Services, and Print Services roles with a read-only Active Directory Domain Services role, you have a "branch office in a box" solution—just add a remote access device such as a VPN router and you're in business.

The File Services role is added by default as part of the base Server Core installation, but you can add additional role services to support additional functionality.

The command used to install a role in Server Core is `Ocsetup.exe`. The exact same command is used to uninstall a role, but with the `/uninstall` command-line parameter. The full syntax for **Ocsetup** is:

```
Ocsetup </?|/h|/help>  
Ocsetup <component> [/uninstall][/passive][/unattendfile:<file>] [/quiet]  
          [/log:<file>][/norestart][/x:<parameters>]
```

The important thing to remember about **Ocsetup** is that it is quite unforgiving. It is case-sensitive, and even a slight mistake in the case of the component name will cause the command to fail.

A script to install the roles for this solution, except the domain controller role, would look like this:

```
@REM filename: SetupBranch.cmd  
@REM  
@REM Setup file to install roles for a branch office server  
@REM  
@REM Created: 5 September, 2007  
@REM ModHist:  
@REM
```



```
@REM Copyright 2007 Charlie Russel and Sharon Crawford. All rights reserved
@REM You may freely use this script in your own environment,
@REM modifying it to meet your needs.
@REM But you may not re-publish it without permission.

@REM Using "start /w" with ocsetup forces ocsetup to wait until it
@REM completes before
going on to the next task.

@REM Install DNS and DHCP
@echo Installing DNS and DHCP roles...
start /w ocsetup DNS-Server-Core-Role
start /w ocsetup DHCP-Server-Core

@REM Now, install File Role Services
@echo Now installing File Role Services...
start /w ocsetup FRS-Infrastructure
start /w ocsetup DFSN-Server
start /w ocsetup DFSR-Infrastructure-ServerEdition

@REM Uncomment these two lines to add NFS support
@REM start /w ocsetup ServerForNFS-Base

@REM start /w ocsetup ClientForNFS-Base

@REM Install Print Server Role

@echo Installing Print Server Role
start /w ocsetup Printing-Server-Core-Role

@REM Uncomment next for LPD support
@REM start /w ocsetup Printing-LPD-Print-Service
```

Note You can't include the **DCPromo** command in the script above because installing the Print Server role requires a reboot, which locks out **DCPromo**.

You cannot use **DCPromo** interactively to create a domain controller—you must create an `unattend.txt` file to use with it. The basic minimum `unattend.txt` file is:

```
[DCInstall]
InstallDNS = Yes
ConfirmGC = yes
CriticalReplicationOnly = No
RebootOnCompletion = No
ReplicationSourceDC = hp350-dc-02.example.local
ParentDomainDNSName = example.local
ReplicaOrNewDomain = ReadOnlyReplica
ReplicaDomainDNSName = example.local
```

```

SiteName=Default-First-Site-Name
SafeModeAdminPassword = <passwd> UserDomain = example
UserName = Administrator
Password = <passwd>

```

Important The passwords fields must be correct, and will be automatically stripped from the file for security reasons. For Server Core, you must specify a *ReplicationSourceDC* value. You should set *ReplicaOrNewDomain* to the value shown here—*ReadOnlyReplica*—to create a read-only domain controller.

To install the read-only Domain Controller role, follow these steps:

1. Use Notepad or your favorite ASCII text editor (we use GVim, which works quite well in Server Core) to create an unattend.txt file with the necessary settings for the domain you will be joining. The specific filename of the unattend file is not important because you specify it on the command line.
2. Change to the directory that contains the unattend file. If the server has any pending restarts, you *must* complete them before promoting the server to domain controller.
3. Run DCPromo with the following syntax:
`Dcpromo /unattend:<unattendfilename>`
4. If there are no errors in the unattend file, DCPromo will proceed and promote the server to be a read-only domain controller, as shown in Figure 9-4.

```

Administrator: C:\Windows\system32\cmd.exe
F:\>Dcpromo /unattend:unattend.txt
Checking if Active Directory Domain Services binaries are installed...
Warning: AutoConfigDNS is deprecated, although it is still supported. Consider
using InstallDNS instead.

Active Directory Domain Services Setup
Validating environment and parameters...

-----
The following actions will be performed:
Configure this server as an additional Active Directory domain controller for th
e domain example.local.

Site: Default-First-Site-Name
Additional Options:
  Read-only domain controller: Yes
  Global catalog: Yes
  DNS Server: Yes

Update DNS Delegation: No
Source DC: hp358-dc-02.example.local

Password Replication Policy:
  Allow: EXAMPLE\Allowed RODC Password Replication Group
  Deny: BUILTIN\Administrators
  Deny: BUILTIN\Server Operators
  Deny: BUILTIN\Backup Operators
  Deny: BUILTIN\Account Operators
  Deny: EXAMPLE\Denied RODC Password Replication Group

Database folder: C:\Windows\NTDS
Log file folder: C:\Windows\NTDS
SYSVOL folder: C:\Windows\SYSVOL

The DNS Server service will be configured on this computer.
This computer will be configured to use this DNS server as its preferred DNS ser
ver.

```

Figure 9-4 Use DCPromo to create a read-only domain controller with an unattend file.

Listing Roles

The `Oclist.exe` command provides a complete list of the available Server Core roles, role services, and features, as well as their current state. Use `Oclist` to get the exact, case-sensitive list of the features and roles you want to install.

Managing a Server Core Computer

Managing a Server Core computer is a different experience for most system administrators. None of the graphical tools you're used to using is available *on the server*. But once you've configured the Server Core computer for remote management, as described under "Initial Configuration" earlier in the chapter, you can create management consoles that point to the Server Core computer, which allow you to do all your tasks from a graphical console.

More Info For details on how to create custom MMCs, see Chapter 14, "Managing Daily Operations."

There are four basic ways to manage a Server Core installation. They are:

1. Locally using a command prompt.
2. Remotely using Remote Desktop. The shell in Remote Desktop will have only the same functionality (a command prompt) as being logged on locally.
3. Remotely using Windows Remote Shell.
4. Remotely using an MMC snap-in from a computer running Windows Vista or Windows Server 2008.

Some tasks are a bit tricky in Server Core—we're used to usually doing them exclusively from the GUI. An obvious task is changing the password on your account. For that, use the `net user <username> *` command. Some of the tasks that can be a problem, and their solutions, are shown in Table 9-2.

Table 9-2 Common Task Workarounds in Server Core

Task	Solution/Workaround
Enable automatic updates	Cscript %windir%\system32\scregedit.wsf /AU [value] Where values are: 1 – disable automatic updates 4 – enable automatic updates /v – view current setting

Table 9-2 Common Task Workarounds in Server Core

Task	Solution/Workaround
Enable Remote Desktop for Administrators	Cscript %windir%\system32\scregedit.wsf /AR [value] Where values are: 0 – enable Remote Desktop 1 – disable Remote Desktop /v – view current setting
Enable Terminal Server clients from Windows versions prior to Windows Vista	Cscript %windir%\system32\scregedit.wsf /CS [value] Where values are: 0 – enable prior versions 1 – disable prior versions /v – view current setting
Allow IPSec Monitor remote management	Cscript %windir%\system32\scregedit.wsf /IM [value] Where values are: 0 – disable remote management 1 – enable remote management /v – view current setting
Configure DNS SRV record weight and priority	Cscript %windir%\system32\scregedit.wsf /DP [value] Where DNS SRV priority values are: 0-65535. (Recommended value = 200) /v – view current setting Cscript %windir%\system32\scregedit.wsf /DW [value] Where DNS SRV weight values are: 0-65535. (Recommended value = 50) /v – view current setting
Update User passwords	Net user <username> [/domain] *
Installing .msi files	Use the /q or /qb switches from the command line with the full .msi filename. /q is quiet; /qb is quiet but with a basic user interface
Changing the time zone, date, or time	timedate.cpl
Change internationalization settings	intl.cpl
Using Disk Management console	From the command line of the Server Core installation: Net start VDS Then run Disk Management remotely.
Get Windows version information	Winver is not available. Use systeminfo.exe instead.
Get Help (regular Windows Help and Support files are not viewable in Server Core)	Cscript %windir%\system32\scregedit.wsf /cli

Using Windows Remote Shell

You can use Windows Remote Shell to remotely execute commands on a Server Core computer. But before you can run Windows Remote Shell, you need to first enable it on the target Server Core computer. To enable Windows Remote Shell, use the following command:

```
winrm quickconfig
```

To run a command remotely, use the **WinRS** command from another computer using the following command:

```
winrs -r:<ServerName> <command string to execute>
```

Using Terminal Server RemoteApp

One neat trick that we like is to use the new TS RemoteApp functionality of Windows Server 2008 to publish a Command Prompt window for the Server Core computer directly onto our desktop. This is simpler and more direct, and saves screen real estate, which is always a benefit. To create an RDP package that you can put on your desktop, follow these steps:

1. On a Windows Server 2008 server that has the Terminal Services role enabled, open the TS RemoteApp Manager, as shown in Figure 9-5.




Figure 9-5 Use the TS RemoteApp Manager to create a remote cmd.exe window.

2. Connect to the Server Core computer you want to build an RDP package for.

3. Click Add RemoteApp Programs in the actions pane to open the RemoteApp Wizard.
4. Click Next to open the Choose Programs To Add To The RemoteApp Programs List page, shown in Figure 9-6.




Figure 9-6 The Choose Programs To Add To The RemoteApp Programs List page of the RemoteApp Wizard

5. Click Browse, and navigate to \\<ServerName>\c\$\windows\system32\cmd.exe. Click Open.
6. Click Next and then click Finish to add the remote program and return to the TS RemoteApp Manager.
7. Select cmd.exe in the RemoteApp programs pane and click Create .rdp File in the actions pane.
8. Click Next, and specify any additional package settings for the RDP package. Note the location where the package will be saved.
9. Click Next twice and then click Finish to create the RDP package.
10. Copy the package to the computer where you will use it.

Now you can open a Command Prompt window directly onto the Server Core computer simply by double-clicking the RDP package you created and saved.

Summary

In this chapter we've covered some basic steps for setting up and configuring the new Server Core installation option of Windows Server 2008. We think this is an exciting new way to get the power of Windows Server while maintaining very high levels of security and ease of management. And yes, we know that sounds a bit like marketing hype, but we actually think that Server Core is an important step forward.

In the next chapter, we'll cover managing and configuring your printers using the Printer Management console.